

Temperature Analysis Profile

This program analyzes the temperature of raw environmental test data for automotive lighting systems. The tests expose lighting systems to various temperature profiles at times with the systems powered. The primary function of this project is to detect if the changing of temperature of each sample and the ambient is as consistent and regular as the particular and regular changed temperature condition.

Input Raw Data Sample

1. Thermal Shock data (CSV.)

	A	B	C	D	E	F	G	H	I	J	K	L	M	N
1	Sweep #	Time	Chan 101	Chan 102	Chan 103	Chan 104	Chan 105	Chan 106	Chan 107	Chan 108	Chan 109	Chan 110	Chan 111	Chan 112 (C)
2	1	02/02/200	-39.67	-36.88	-39.16	-38.98	-38.57	-38.00	-38.64	-38.85	-39.22	-38.58	-38.60	-39.23
3	2	02/02/200	0.71	-21.09	-20.88	-19.07	-30.03	-23.05	-7.16	4.02	-5.03	-19.62	-0.94	-32.58
4	3	02/02/200	41.51	-9.48	-5.90	-1.35	-19.17	-6.09	11.60	32.44	19.63	-2.16	34.37	-22.41
5	4	02/02/200	62.64	-1.90	6.50	12.53	-9.15	8.15	24.15	50.90	37.16	13.32	58.98	-11.98
6	5	02/02/200	75.47	5.01	18.25	24.16	0.20	20.52	34.44	66.14	51.61	27.72	76.56	-2.82
7	6	02/02/200	81.49	10.23	26.76	32.85	8.11	30.11	40.21	75.39	61.89	38.97	86.71	5.64
8	7	02/02/200	85.29	14.79	35.49	40.49	15.56	38.18	46.55	83.57	70.48	49.10	93.83	13.81
9	8	02/02/200	88.05	18.90	42.56	47.72	22.25	44.71	51.97	90.08	77.23	57.66	98.75	21.75

(And so on...)

2. PTC data (CSV. or TXT.)

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	R	S	T	U	V	W
1	Date	Time	Amb Temp	TC2	TC3	TC4	VSetpoint	VSense 1	VSense 2	Board on	TP1: Syst	TP2: Syst	TP3: Syst	TP4: Syst	TP5: Syst	TP6: Syst	TP7: Syst	TP8: Syst	TP9: Syst	TP10: Syst	TP11: Syst	TP12: System	93
2	2/6/2017	6:50:57 PM	-42.518	-42.032	6.50E+34	-42.125	9	0.003	0.003	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
3	2/6/2017	6:51:03 PM	-42.594	-42.025	6.50E+34	-42.146	9	0.003	0.003	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
4	2/6/2017	6:51:09 PM	-42.702	-42.049	6.50E+34	-42.132	9	0.004	0.003	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
5	2/6/2017	6:51:15 PM	-42.777	-42.042	6.50E+34	-42.129	9	0.004	0.004	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
6	2/6/2017	6:51:21 PM	-42.842	-42.056	6.50E+34	-42.143	9	0.003	0.003	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
7	2/6/2017	6:51:27 PM	-42.889	-42.042	6.50E+34	-42.163	9	0.004	0.005	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
8	2/6/2017	6:51:33 PM	-42.918	-42.063	6.50E+34	-42.16	9	0.003	0.004	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	
9	2/6/2017	6:51:39 PM	-42.921	-42.056	6.50E+34	-42.19	9	0.005	0.005	0	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	OFF	

(And so on...)

Current Limits

This program can only analyze the cycles that can reach the threshold, but will leave those cycles cannot reach as blank.

Core Functions


1. Temporal Plotting

2. Summary Tables with basic statistics

- List out of range data (Usually because of reading errors or opened thermal couple)
- Statistic summary of all the cycles
- List out all the calculate result of each cycle: (the attributes listed as below)
 - Cold_soak_duration_minute
 - Cold_soak_mean_temp_c
 - Cold_soak_max_temp_c
 - Cold_soak_min_temp_c
 - Hot_soak_duration_minute
 - Hot_soak_mean_temp_c
 - Hot_soak_max_temp_c
 - Hot_soak_min_temp_c
 - Down_recovery_time_minute
 - Down_RAMP_temp_c
 - Down_RAMP_rate_c/minute
 - Up_recovery_time_minute
 - Up_RAMP_temp_c
 - Up_RAMP_rate_c/minute

Introduction

1. Gui



The screenshot shows a software window titled "Temperature Profile Analysis". It features two radio buttons at the top: "PTC" (unselected) and "Thermal Shock" (selected). Below these, there is a "Select Data Folder" button and a text field containing the path "C:/Users/s.chen6/Desktop/Temp Profile Analysis/test_data". Further down, there are five input fields: "Test Name:" with the value "TShock test sample", "Upper Threshold (°C):" with the value "95", "Lower Threshold (°C):" with the value "-40", "Temperature Tolerance (°C):" with the value "3", and "Component rate adjustment (%):" with the value "10". At the bottom of the form is a "Load TCs..." button.

- In this interface, user provides inputs to this program. * Choose the folder which include the raw test data files.
- (the files could be one or many, if many, please rename them by the time order. For instance, dat00001.csv, dat00002.csv and dat00003.csv).
- Choose the type of test.
- Give a name or description to this data file in Test Name box.
- Input the Upper & Lower Threshold, and Temperature Tolerance.
- Input Component rate adjustment if it exists. (if none leave blank)

Temperature Profile Analysis

☐ PTC ☒ Thermal Shock

Select Data Folder: C:/Users/s.chen6/Desktop/Temp Profile Analysis/test_data

Test Name: TShock test sample

Upper Threshold (°C): 95

Lower Threshold (°C): -40

Temperature Tolerance (°C): 3

Component rate adjustment (%): 10

Load TCs...

Amb Temp Channel: 112

Chan 101 (C): U7 Chan 111 (C):

Chan 102 (C): U8 Chan 112 (C): ambient

Chan 103 (C): Z1

Chan 104 (C): Z2

Chan 105 (C):

Chan 106 (C):

Chan 107 (C):

Chan 108 (C):


Chan 109 (C):

Chan 110 (C):

Analyze!

- In this interface, this program can detect how many channels are in this test.
- User can label which channel is the Ambient.
- User can include a brief label for each channel or leave it blank.
- All of these brief labels will show in the worksheet tab of output excel file.


2. Analyze! (Click "Analyze!" Button)





```
C:\windows\py.exe
Upper Threshold: 95
Lower Threshold: -40
Channels: <'Chan 102 <C>': 'U8', 'Chan 105 <C>': '', 'Chan 111 <C>': '', 'Chan 1
12 <C>': 'ambient', 'Chan 109 <C>': '', 'Chan 108 <C>': '', 'Chan 101 <C>': 'U7'
, 'Chan 104 <C>': 'Z2', 'Chan 103 <C>': 'Z1', 'Chan 107 <C>': '', 'Chan 106 <C>
': '', 'Chan 110 <C>': ''>
Amb Channel: 112
C:\Users\s.chen6\AppData\Local\Programs\Python\Python35\lib\site-packages\plotly
\napi\vt\clientresp.py:40: UserWarning:
Estimated Draw Time Too Long
The draw time for this plot will be slow for all clients.
inside tshock_analyze_all_channels...
inside ambient_analysis...
STARTING POINT: HIGH SOAK
Chan 101 <C>
STARTING POINT: HIGH SOAK
Chan 102 <C>
STARTING POINT: HIGH SOAK
Chan 103 <C>
STARTING POINT: HIGH SOAK
Chan 104 <C>
STARTING POINT: HIGH SOAK
Chan 105 <C>
STARTING POINT: TRANSFORM UP
Chan 106 <C>
STARTING POINT: HIGH SOAK
Chan 107 <C>
STARTING POINT: HIGH SOAK
Chan 108 <C>
STARTING POINT: HIGH SOAK
Chan 109 <C>
STARTING POINT: HIGH SOAK
Chan 110 <C>
STARTING POINT: HIGH SOAK
Chan 111 <C>
STARTING POINT: HIGH SOAK
Chan 112 <C>
ANALYSIS COMPLETE.
```

- In this interface, the notification can show the progress of analysis, and also can show how the channel start.

3. Plotting



- This is the general plot of raw test data.
- The X axis is the time scale and index.
- The Y axis is the temperature(C) over that scan.
- This graph can show only selected channels, and also can zoom in and out.
- The easiest way to save the graph is to take a snippet and save as a png file type



4. Output Excel

1	Version 4.0					
2						
3	In this TSHOCK test file, there are 68 cycles.					
4						
5	The First Table: List out the test data that have reading error.					
6		Sweep #	Time	Chan 112 (C)		
7						
8						
9						
10	The Second Table: Summary table for the ambient.					
11						
12						
13						
14						
15		cold_soak_duration_minute	cold_soak_mean_temp_c	cold_soak_max_temp_c	cold_soak_min_temp_c	hot_soak_duration_minute
16	mean	16.3	-41.74	-37.46	-43.17	13.72
17	min	16.17	-41.84	-37.91	-43.6	13.5
18	min_cycle#	5	45	65	59	11
19	max	16.5	-41.63	-37.07	-42.89	13.83
20	max_cycle#	62	39	1	63	42
21	std_dev	0.1	0.05	0.23	0.14	0.08
22						
23						
24						
25	The Third Table: List out the calculation result for each cycle of ambient.					
26						
27						
28						
29						
30	cycle#	cold_soak_duration_minute	cold_soak_mean_temp_c	cold_soak_max_temp_c	cold_soak_min_temp_c	hot_soak_duration_minute
31	1	16.33	-41.79	-37.07	-43.17	13.67
32	2	16.33	-41.76	-37.32	-43.32	13.67
33	3	16.33	-41.77	-37.39	-43.16	13.67
34	4	16.33	-41.8	-37.53	-43.36	13.67
35	5	16.17	-41.78	-37.77	-43.11	13.67
36	6	16.33	-41.7	-37.3	-43.15	13.67

- Each worksheet tab of the output excel represent one channel.
- Each worksheet consists of 3 tables as displayed above.

5. Independency

- [Python3](#)
- [Pandas](#) - Data wrangling and processing
- [Matplotlib](#) - Plotting
- [XlsWriter](#) - Creates analysis tables
- [PyQt5](#) – GUI

Authors

- Siyu Chen
- Sam Bruno